

1 Configuration of AIP QM Streamlined Data Processing

Basic configuration

This document describes the steps necessary in order to achieve streamlined data processing for AIP terminals as part of CAQ 8.1 inspection results recording.

Streamlined data processing includes four different sections:

1. *Disabling of failure and/or measure processing* → see Configuration_AIP-QM.doc → can be performed by modifying dynamic dialogs and workflow settings

The other three sections require minimum software versions (see below) and implementation of option 1214:

2. disabling the list of automatic errors
3. reducing dialog data
4. disabling control charts

Please proceed as follows:

Option 1214 - AIP CAQ streamlined data processing

Install & activate

On the HYDRA server please start the MS-DOS prompt from the "HYDRA administration" directory on the desktop (for Windows) and/or connect to the HYDRA server via Telnet connection (for UNIX).

Execute the following command:

```
hydscr.exe db_sql/dbp_caq82_option_1214.hsc
```



Optionally, the following command can be executed:

```
hydscr.exe db_sql/dbp_caq82_status_rk.hsc
```

This cancels disabling of control charts.

Configuration / functional description

System Availability

MW 3.0 (server)	MW 2.1 (server)	AIP	CTWIN	Console	MOC	Miscellaneous
		X				

Valid values

Y/N

Valid from HYDRA-CAQ versions onwards:

caq_dc_t.dll >= 2.0.2.36

caq72.dll >= 2.0.2.28

mpdv-aip.zip >= 15 February 2015

Area-dependent

no

Description

If this option is enabled processing and collection of inspection data can be simplified and therefore accelerated at AIP CAQ terminals by making different entries in the "addition" field.

The following can be entered in the "addition" field:

- [SKIP_RK]
- [SLIM_DATA]
- [SKIP_AET]

The different entries do *not depend* on each other and can be combined in *any* way.

They are separated by commas in the "addition" field.



These functions are not available for QMS.

[SKIP_RK]

Processing and display of control charts are disabled for the following input types in the dialogs for inspection results recording.

- BEWERT_STICHPR_PPUNKT_SIMPLE
- BEWERT_STICHPR_SIMPLE
- MESSW_ESTCK_PPUNKT_SIMPLE
- MESSW_ESTCK_STICHPR_SIMPLE



If processing and display of control charts are only to be disabled for specific input types, this is can be achieved in the relevant status of the "ERFASSART" status type. By removing the parameter "[RK]", the control chart function is disabled for the relevant input type. For further details please refer to the status documentation entitled "Configuration_QM_Status".

Displaying of control charts may be enabled and/or disabled for specific terminals (or terminal groups) via the AIP configuration file "caq_dc_t.ini", which also overrides any option set. Further details can be found in the document entitled "AIP_Configuration_caq_dc_t".

When activated subsequently, the parameter [RK] has to be added to the relevant status for the mentioned input types, provided that control charts should be displayed.

[SLIM DATA]

Adding of data filters to reduce the data volume when calling up the dialogs for inspection results recording, which accelerates processing.



Default filters can be changed in the AIP configuration file "caq_slim_data.ini" within the folder .\packets\. If changed, this file is to be stored in the custom directory on the server.

[SKIP AET]

Processing and display of automatic failure lists are disabled for specific dialogs of inspection results recording.

The following input types support processing of automatic failure lists:

- BEWERT_STICHPR_PPUNKT_SIMPLE
- BEWERT_STICHPR_SIMPLE
- MESSW_ESTCK_PPUNKT_SIMPLE

- MESSW_ESTCK_STICHPR_SIMPLE



Further configuration details can be found in the document entitled "Configuration_AIP-QM".

Updating the HYDRA terminal clients (AIP)

1. Update the program version of HYDRA terminal clients.

There are different possibilities:

A) Direct installation at the terminal:

- Restart the terminals.
- In the start menu of the terminal download the programs from the server using the menu item "**Load Application**".

B) Remote installation via the MOC client

- Choose the option
"**Reload program**"
in the MOC terminal configuration - terminal administration

2. After installing the terminal update, verify if the program version in the terminal configuration of the MOC client corresponds to that version listed on the delivery note.

Further configurations/requirements

- Availability of the configuration file `.\packets\caq_slim_data.ini`
- Availability of the terminal script ZIP `mpdv-aip.zip` (at least version dated 15 February 2015)
- Availability of the software `caq72.dll` (version $\geq 2.0.2.28$)
- Availability of the software `caq_dc_t.dll` (version $\geq 2.0.2.36$)



The configuration document entitled "Configuration_AIP-QM" describes how the relevant functions can be configured / activated.