

# 1 List of Inspection Points

On the left hand side a list containing all auditable inspection points appear. The list can be restricted using a filter. A match code filter is available for the user. Content to be filtered in a text is replaced by the symbol "\*". Using the symbol "?" an individual symbol can be replaced. The complete content of the inspection point list can be filtered. The following information is part of the inspection point list:

- Order - operation  
Both are separated with a hyphen and are shown in the first line of the inspection point. Example of a display format: 12345678 – 0010“ („12345678“ is the order number, „0010“ is the operation).
- Article number - article description - date of when inspection point was created  
The information is part of the 2. line and are also separated by a hyphen.

Also, the status of an inspection point result is highlighted by a colored LED symbol. The following color assignments are valid:

- o.k. => green LED
- fail => red LED => rote LED

A special filter containing can be requested by the filter symbol to look for the area and the inspection point status. This is in addition to the possibility to filter using a match code. To facilitate the filter process corresponding selection lists are available. .

In the right display area detailed information is shown in the list for the selected inspection point. The parallel display of the left and right display area is dependent on the selected device. On a smartphone only the inspection list is shown. In order to show details the required inspection point should be selected.

The detailed display enables using special function buttons for the following create/process function:

- Request the characteristics list
- Editing inspection point
- Completion of inspection point

Based on the inspection result of the corresponding inspection point characteristics when the function "Completion of inspection point" is triggered, the inspection point usage decision is automatically identified and the inspection is completed at the same time.