

1 Configuration of Machine Pictures for the MOC Application Workplaces/Machines

Usage

This document describes the configuration required to display images in the MOC application [workplaces/machines](#).

Prerequisites


The pictures (files) have to be stored in a directory that may be accessed from the system.

Procedure

1. Store the files to be displayed in a central directory that may be accessed using the system's means of communication.
2. Make sure the user who accesses the directory has the relevant authorizations.
3. Set the path configuration for the logical path MOCWPIMG. Further information on the path configuration can be found [here](#).

Example of a path configuration


(The files are stored locally on the Windows HYDRA Server):



The screenshot shows a window titled 'Edit' with a 'Main page' tab. It contains a form with the following fields:


Path	MOCWPIMG
Protocol	file
Host	localfile
Port	0
URL path	g:\hydra4\4\grafik\bde
User	hydadm
Password	
Description	MOC path for workplace images

- Enter a valid file name in the field "file name" of the [workplace/resource configuration](#) application.



Result

The picture is shown in the MOC application [workplaces/machines](#):



Trouble Shooting

If the picture is not shown (message: "No data available"), the reason for this can be determined by evaluating the LOG file on the server. To do so, proceed as follows:

- On the server go to the subdirectory ...\\JHYDRADIR\\<System>\\err, where the web service calls are recorded for the system. As a general rule, it can be found within the system directory on the HYDRA server, e.g. g:\\hydra4. In case of doubt, please contact MPDV Support.
- Search for the current LOG file in the directory. This is the file with the extension ".log".
- Open the LOG file by using an editor (attention: the LOG file might be very large!) and search for the error message, as mentioned below for example.

4. Check the displayed file name and the displayed path (highlighted in red).

Please note: If necessary, you even have to search in LOG files with older time stamps, provided that the message occurred some time ago.


Error message in the LOG file (e.g. hydra-java-4.log)

```
2012-12-02 14:08:07,024 ERROR http-8083-2 -  
(de.mpdv.plugin.service.bopDocLinks.BopDocLinksList.doService():-1) - 1 - 7c8d71a2-cc0c-406e-  
aald-50168927deab - 76 - Error opening graphic file 33021.jpg in HYDRA path MOCWPIMG. Exception  
was:  
de.mpdv.common.data.hyPath.exceptions.UnreachableHyPathException: Could not open file:  
\\scc5D:\Hydra72\1\grafik\bde  
    at  
de.mpdv.common.hyPath.pathResolver.FileHyPathResolver.checkHyPath(FileHyPathResolver.java:124)  
    at de.mpdv.common.hyPath.HydraPathManager.checkPath(HydraPathManager.java:545)  
    at de.mpdv.common.hyPath.HydraPathManager.openFile(HydraPathManager.java:131)  
    at de.mpdv.plugin.service.bopDocLinks.BopDocLinksList.doService(Unknown Source)  
    at  
de.mpdv.mesClient.businessService.impl.ServiceDispatcher.doInteract(ServiceDispatcher.java:238)
```


Possible reason: wrong path configuration

In this example, the pictures are stored on another server than the HYDRA server. For this reason, the HYDRA server (Windows) needs to access another server (Windows). The drive letter (here: "g:") for the remote server has been entered in the URL path field of the path configuration.

Wrong path configuration



Main page	
Path	MOCWPIMG
Protocol	file
Host	scc5
Port	0
URL path	g:\Hydra72\1\grafik\bde
User	hydadm
Password	
Description	MOC path for workplace images

Correct path configuration**Possible reason: access by user/password denied**

The MOC client does not directly access the path but the Java Server (Tomcat) that in turn provides the MOC client with the image. As Tomcat is running as service, the server uses the service account user for accessing the file.

For this reason, it is to be checked whether the file included in the shared path can also be accessed from the server. If this is the case, another check has to be made as to whether only specific combinations of users/passwords might be able to access the path.